

## DSM2 Bay-Delta Tutorial 3: Source Tracking (Fingerprinting)

**Purpose:** The purpose of this tutorial is to use the source tracking capabilities of the model to create a fingerprinting study. We will set up both volumetric and concentration-based fingerprinting and visualize the results.

### 1. Reopen the historical tutorial

- a. In windows, navigate to `\{DSM2_home\}\tutorial\historical`.
- b. In the GUI, open `historical_tutorial`.

### 2. Create a model for source tracking:

In the background, source tracking imposes a computational cost on QUAL that is the same as one additional constituent per source. For this reason, it is courteous to create an entirely separate model for source tracking.

- a. In the GUI, navigate to the simulation.
- b. Right click and create a new model. Name it *historical\_tutor\_qual\_fingerprint*.
- c. Add the layer *qual\_standard\_parameters*.
- d. Add the standard historical EC model layers. Go to the Boundary Concentration page. Add the *delta\_historical\_qual* and *dicu\_ec* layers.

### 3. Define the source groups.

- a. Groups are defined in the QUAL Groups View. Group matching criteria reference the same boundary names that are created in hydro and matched in the boundary concentration assignments.
- b. Create a layer called `tutorial_fingerprinting`. Look at the boundary inputs and devise patterns that will isolate:
  - 1) `mtz`: Martinez tidal boundary
  - 2) `sjr`: Vernalis on the San Joaquin River
  - 3) `sac`: match Sacramento River and Yolo. You can use two group members or a single member with the `(sac|yolo)` syntax.
  - 4) `ag`: All the DICU – don't forget BBID in the reservoir source-sinks. You will find the dot-star wildcard useful for this (`dicu_.*` or `dicu_drain_.*`).

5) east: match the eastside streams such as calaveras, make, consumnes.

#### **4. Define volumetric inputs**

- a. Create a layer called *tutorial\_volumetric\_fingerprint* in the Boundary Concentration view. Go through each of the time series input panels for QUAL and create an equivalent input that has a constant value of 100. Call the constituent *volume*. Hint: for the ag sources, you will want to do some of your work in Excel so that you can cut and paste.

#### **5. Define the fingerprinting output**

- a. Specify Clifton Court concentration output for each of the source groups that you defined for both EC and *volume*. The name should be *clifton\_court*, the concentration should be *ec* or *volume* and the interval should be 1day. Avoid redundancy -- you do not need to put the constituent name or the source into the output name: ie, use “*clifton\_court*” for the name, not “*clifton\_ag*” or “*clifton\_ec*”.

#### **6. Run HYDRO and QUAL for One Year**

- a. Change the model name in *qual\_ec.inp* and run HYDRO and QUAL for one year in 2002. Start QUAL a day later to avoid mass conservation errors in the first hour. Make sure the *init\_conc* variable is set to zero so that there will be no initial condition contribution for any variables (note: this is not always the case -- for a volumetric fingerprint, it may be useful to make this concentration 100 if you want to include initial conditions in the fingerprint analysis).

#### **7. Process the output**

- a. Use VISTA or HEC-DSSVUE to open up the output file. Copy May-September concentrations for each location. Paste the output into a new sheet in the Excel provided called *excel\_fingerprint.xls*, which you can use as a reference. Use the “stacked area plot” in Excel (one of the standard Excel plot types) to plot up the fingerprint results.