

VIII. Tutorial 7: Delta SIMULATIONS with HYDRO and QUAL

1. Clone the Historical Simulation:

- a. In the file menu of the GUI, select *Clone Simulation*.
- b. In the *Clone Simulation* window, select *historical*.
- c. Name the cloned simulation, *historical_tutorial*.
- d. Rename the QUAL models:
 - 1) In the *Sessions Navigator*:
 - i) Locate the directory, *model: historical_tutorial_qual1*.
 - ii) Right-click on the directory and select *Edit Model Properties*.
 - iii) Change the name to *historical_tutorial_qual_ec*.
 - iv) Repeat this process for *historical_tutorial_qual2*, except rename this model, *historical_tutorial_qual_do*.

2. Reset Model Name Parameters in the Text Input Files:

- a. In Windows Explorer, navigate to the directory,
`{DSM2_home}\tutorial\simulations\historic`
- b. Change the model name environmental variable for HYDRO and QUAL:
 - 1) Open the file, *hydro.inp*.
 - i) Under the SCALAR section, locate the environmental variable,
model_name.
 - ii) Note that *model_name* itself contains the environmental variable:
SIMNAME.
 - iii) *SIMNAME* is not listed anywhere in the *hydro.inp* file. In fact, it is listed in the *config-hist.inp* file.
 - 2) Open the file, *config-hist.inp*.
 - i) In the ENVVARS section, locate *SIMNAME*.
 - ii) Change its value from *historical* to *historical_tutorial*.
 - iii) Save *config-hist.inp*.
 - 3) Because *qual_ec.inp* and *qual_do.inp* both utilize the environmental variable, *SIMNAME*, these files do not have to be modified.

- c. Change the model name environmental variable for PTM:
 - 1) Open the file, *ptm.inp*.
 - i) Under the SCALAR section, locate *model_name*.
 - ii) Note that it is set to the different environmental variable, *MODEL_NAME*.
 - iii) This environmental variable is listed in the ENVVARS section of this file.
 - iv) Change the value of *MODEL_NAME* from *needs_hydro* to *historical_tutorial_hydro*, and save the file. Note that PTM requires the grid from HYDRO.
 - v) Save *ptm.inp*.
- d. Change the Time Interval Environmental Variable:
 - 1) In the GUI, the value given for all channel output is given as $\${FINE_OUT}$. If you would like to verify this, you can check the *Channel Output* view of the *Output Time Series* directory for the HYDRO setup.
 - 2) Navigate back to the *config-hist.inp* file:
 - i) Locate *FINE_OUT* under the ENVARRS section.
 - ii) Change its value from *15MIN* to *1HOUR*.
 - iii) Save *config-hist.inp*.
- e. Select the Proper Database:
 - 1) In *hydro.inp*:
 - i) Find the SCALAR section.
 - ii) Change the *database* entry to the following:

database dsm2input_access
 - iii) Repeat this procedure for *qual_ec.inp*, *qual_do.inp*, and *ptm.inp*.
- f. Change the Temporary Directory:
 - 1) In *hydro.inp*, *qual_ec.inp*, *qual_do.inp*, and *ptm.inp*
 - i) In the SCALAR section, find the environmental variable, *temp_dir*.
 - ii) Change the value to *c:\temp* or a temp directory with ample free space.
 - iii) Remember to repeat this procedure for all four files.
 - iv) Save the four files.

3. Run HYDRO:

- a. In Windows Explorer, navigate to the directory,
`{DSM2_home}\tutorial\simulations\`
- b. Right-click on the *historic* directory, and select, *Open Command Window Here*.
- c. In the command window, type: `dsm2 hydro config-hist.inp`.
- d. Wait for HYDRO to complete its runs.

4. Replicate HYDRO's tidefiles and modify QUAL's input file to make them suitable for a Multi-tidefile Run:

- a. In Windows Explorer, navigate to the directory,
`{DSM2_home}\tutorial\simulations\historic\output`
- b. Locate the *hist.h5* tidefile and copy-and-paste this file three times in the same directory. These copies will emulate hydro tidefiles generated on three separate machines.
- c. Rename the copies: *tf1.h5*, *tf2.h5*, and *tf3.h5*.
- d. Open *qual_ec.inp*:
 - 1) If necessary, make corrections so that the TIDEFILE section looks as follows:

```
TIDEFILE
START_DATE  END_DATE  FILENAME
#runtime    length    output/hist.h5
runtime     20JUL1996  output/tf1.h5
20JUL1996   24JUL1996  output/tf2.h5
last        length    output/tf3.h5
01SEP1996   length     fictitious.h5
END
```

- 2) With the exception of the commented-out (#) statement, these statements direct QUAL to the *hydro/output* location storing the tidefiles needed for the multi-tide run. The start and end date show the possibilities: using a real date, runtime (start of the simulation), length (go to end of tidefile) and last (start where the last tidefile left off).
- 3) Change the temporary directory from `z:\temp` to a temp location with ample free storage.
- 4) Save *qual_ec.inp*.

5. Run QUAL:

- a. In the command window, type: `dsm2 qual_ec config-hist.inp`.

6. Running QUAL with Nonconservative Constituents and a Single Tidefile:

- a. In Windows Explorer, navigate to the directory,
`d:\{DSM2_home}\tutorial\simulations\historic`
- b. Open `qual_do.inp`.
 - 1) In the TIDEFILE section, ensure that only one row for tidefiles is present and uncommented. This should be the row associated with the file, `hist.h5`.
 - 2) Change the temporary directory from `z:\temp` to a temp location with ample free storage
 - 3) Save the `qual_do.inp` file.
- c. Open `config-hist.inp`.
 - 1) In the ENVVARS section, locate the environmental variable, `DSM2MODIFIER`.
 - 2) Change the value from `hist` to `nonconserve`.
 - 3) Save `config-hist.inp`.
- d. In the command window, type: `dsm2 qual_do config-hist.inp`.

IX. Tutorial 8: Delta SIMULATIONS with PTM

1. Modify the PTM Input file to Turn On the Dispersion Parameters:

- a. In Windows Explorer, navigate to the directory,
`\{DSM2_home}\tutorial\simulations\historic\`
- b. Open the file, `ptm.inp`.
 - 1) In the TIDEFILE section, ensure that only one row for tidefiles is present.
This should be the row associated with the file, `hist.h5`.
 - 2) Locate the GROUPS section.
 - 3) Add two groups to the list:

<code>sac_below_chipps</code>	<code>channels</code>	<code>range:438-441</code>
<code>sac_below_chipps</code>	<code>channels</code>	<code>(443 452)</code>

4) Locate the GROUP_OUTPUT section.

5) Add this group_outputs to the list:

```
sac_below_chipps 1hour ${PTMOUTPUTFILE} SAC_BELOW_CHIPPS
```

6) Locate the SCALARS section.

7) Change all of the dispersion parameters from *f* to *t*.

```
ptm_ivert      t      # Use Vertical velocity profile
ptm_itrans     t      # Use Transverse velocity profile
ptm_iey        t      # Use transverse mixing
ptm_iez        t      # Use vertical mixing
```

2. Run PTM and Examine the Results:

a. In the command window, type: *dsm2 ptm config-hist.inp*.

b. In Windows Explorer:

1) Navigate to the directory,

```
{DSM2_home}\tutorial\simulations\historic\output
```

2) Examine the output in the *ptmout.txt* file.

3) Copy the files, *anim_db.bin* and *ptmout.txt*.

4) Navigate to the directory,

```
{DSM2_home}\tutorial\simulations\historic\ptm-animate\dual\left_panel
```

5) Paste the files in the *left_panel* directory.

3. Now to See the Effects of having the Dispersions Parameters Turned Off:

a. In Windows Explorer, navigate to the directory,

```
{DSM2_home}\tutorial\simulations\historic\
```

b. Open the file, *ptm.inp*.

1) Locate the SCALARS section.

2) Change all of the dispersion parameters from *t* to *f*.

```
ptm_ivert      f      # Use Vertical velocity profile
ptm_itrans     f      # Use Transverse velocity profile
ptm_iey        f      # Use transverse mixing
ptm_iez        f      # Use vertical mixing
```

c. In the command window, type: *dsm2 ptm config-hist.inp*.

- d. In Windows Explorer:
 - 1) Navigate to the directory,
`{DSM2_home}\tutorial\simulations\historic\output`
 - 2) Copy the files, *anim_db.bin* and *ptmout.txt*.
 - 3) Navigate to the directory,
`{DSM2_home}\tutorial\simulations\historic\ptm-animate\dual\right_panel`
 - 4) Paste the files in the *right_panel* directory.
 - 5) Navigate to the directory,
`{DSM2_home}\tutorial\simulations\historic\ptm-animate`
 - 6) Double-click on *dual.bat* to open the animator.
 - 7) Press start to start the animator and use the controls to adjust the speed.

4. Modifying the Animator Display [optional]:

- a. The *left_panel* and *right_panel* directories contain files needed for operation:
 - 1) *fluxInfoDB.data* stores path information for the PTM output.
 - 2) *labelsDB.data* stores labels information.
 - 3) *network.dat* stores x- and y-locations for nodes and channels.
- b. Examine these files.

5. Changing an Operator Rule:

- a. Bring up the GUI.
- b. In the *Sessions Navigator*:
 - 1) Expand the folder, *model: historical_hydro*.
 - 2) Expand the *Operations* folder.
 - 3) Double-click on *Operating Rules*.
- c. In the *Layers* panel, click on *Layer 1* so that it is the only layer viewed.
- d. Examine the rules for this gate at the Montezuma Slough.
- e. Add a New Operating Rule Layer:
 - 1) In the *Layers* panel, right-click and select *New layer*.
 - 2) Select *Yes* to confirm the refresh.

- 3) Name the layer, *modified_montezuma_ops*.
- 4) The layer will be number 4.
- f. In the *Layers* panel, right-click and select *Set Edit Layer*.
- g. In the *Select Layer* window, double-click *Layer 4*.
- h. In the *Expressions table*:
 - 1) Right-click and select *Insert row*.
 - 2) Enter the information in the appropriate fields for the new row:
 - i) Name: *mscs_calc*
 - ii) Definition: *SEASON > 01AUG OR SEASON < 01FEB*
- i. Save the current settings.
- j. Unset the editing layer.
- k. In the *Sessions Navigator*:
 - 1) Expand the *model: historical_tutorial_hydro* folder.
 - 2) Expand the *Output Time Series* directory.
 - 3) Double-click on *Gate Output*.
- l. In the *Layers* panel, right-click and select *Add layer*.
- m. In the *Select Layer* window, double-click *grid_output*.
- n. In the *Layers* panel, right-click and select *Remove layer*.
- o. Select *std_output_hydro_named* (note, if you omit this step there will be too many output specifications and the model will crash).
- p. Rerun HYDRO:
 - 1) In the command window, type: *dsm2 hydro config-hist.inp*