
# IX. Appendix A – Installation Instructions


### 1. Verify the *Informix* Driver is Installed:

- a. In Windows:
  - 1) Navigate to the Control Panel.
  - 2) Double-click on Administrative Tools.
  - 3) Double-click on Data Sources (ODBC).
  - 4) Select the *Drivers* tab.
  - 5) Check to see if the *IBM INFORMIX ODBC DRIVER* (version 2.9 or higher) is on the list.




- 6) If your computer has this or a later version of the driver, the older version does not have to be installed. Skip to the next section.
- 7) If your computer has no *Informix* driver:
  - i) Open the \dsm2\_training\install directory:
    - (a) Create a new directory called *Informix Setup*.

- (b) Double-click on *clientsdk.2.90.TC1.zip*, and extract the files to the new *Informix Setup* directory.
- (c) Open the *Informix* directory and double-click *setup.exe*.
  - (i) Click Next >.
  - (ii) Accept the license agreement and click Next >.
  - (iii) Enter any <u>User Name and Organization and click Next >.</u>



- (iv) Select a Custom setup and click Next >.
- (v) Accept the default directory and click Next >.

(vi) Deselect everything but the *IBM Informix ODBC Driver* by left-clicking and selecting the red **x**. Then click *Next* >.




- (vii) Click Install.
- (viii) Click Finish.


#### 2. Establish an ODBC data source for the *Informix* Database.

- a. If you do not have an *Informix* account, you must first obtain one from the Computer Assistance section of the Bay-Delta Office. Email Mike Mullen at <a href="mmullen@water.ca.gov">mmullen@water.ca.gov</a>, and he will send you a password.
- b. Navigate to the Control Panel.
- c. Double-click on Administrative Tools.
- d. Double-click on Data Sources (ODBC).
- e. Select the System DSN tab and click Add....

f. Select the IBM INFORMIX ODBC DRIVER and click Finish.



g. Under the *General* tab, enter *dsm2input* for the *Data Source Name*, and provide a description.



h. Under the Connection tab, enter the following information:

1) Server Name: ius\_dminfo\_tcp


2) Host Name: 136.200.32.24

3) Service: 1538

4) Protocol: olsoctcp

5) Database Name: dsm2input6) User Id: use your username

7) Password: enter the password provided by Computer Assistance (Mike Mullen or Tim Tran).




- 8) Click the Apply & Test Connection button.
- 9) If connection was successful, click OK.
- 10) Click *OK* to accept the degradation message.




# 3. Establish an ODBC Data Source for the Microsoft Access Database.


- a. In Windows:
  - 1) Navigate to the Control Panel.
  - 2) Double-click on Administrative Tools.
  - 3) Double-click on Data Sources (ODBC).
  - 4) Select the System DSN tab.
  - 5) Click the Add Button.



6) Select the Microsoft Access Driver (\*.mdb) and click Finish.




- 7) In the ODBC Microsoft Access Setup Window:
  - i) For the Data Source Name, type dsm2input\_access.



- ii) In the *Database* section, click on <u>S</u>elect...
- iii) In the Select Database window:

- (a) Under the *Drives* section, select the drive letter where the tutorial is stored.
- (b) Under the *Directories* section, navigate to *d:\dsm2\_training\dbase*.
- (c) Under the *Database Name* section, select *DSM2input.mdb*.




- (d) Click OK.
- iv) In the ODBC Microsoft Access Setup Window, click OK.

# 4. Configure the JDBC Connection:


- a. In the GUI:
  - 1) Click on the *Tools* menu.
  - 2) Select Configure Database.
  - 3) For the *JDBC URL*, enter the following (case-sensitive): jdbc:informix-sqli://136.200.32.24:1538/dsm2input:informixserver=ius\_dminfo\_tcp
  - 4) For the JDBC driver, enter (case-sensitive): com.informix.jdbc.lfxDriver

5) Enter your username and *Informix* password.



# 5. Select either Informix or Access for your DSM2 Database:

- a. In the GUI:
  - 1) Click on the Tools menu.
  - 2) Select Configure Database.
  - 3) Here is where you select which database to use.
    - i) For *Informix*:
      - (a) Select JDBC Source.



- (b) Make certain the proper information is given in the *JDBC URL* and *JDBC driver* input boxes. (See previous section if necessary)
- ii) For Microsoft Access:
  - (a) Select ODBC source (named in system files).



(b) Fill-in the name of the *ODBC DSN* in that box. This will match the name given in the *Data Sources (ODBC)* window of the *Administrative Tools* of the *Control Panel*.

# 6. Install the Necessary Fortran Drivers:

- a. In Windows Explorer:
  - 1) Navigate to the directory, \dsm2\_training\install.
  - 2) Double-click on VFRUN66Bl.exe.
  - 3) If you receive an overwrite message on a .hlp file, click yes.

### 7. Install the *Open Command Prompt Here* program:

- a. In Windows Explorer:
  - 1) Navigate to the directory, \dsm2\_training\install.
  - 2) Double-click on the CommandPromptHere directory.
  - 3) Right-click on CMDHERE.INF, and select Install from the menu.

# 8. Check Your Version of Java:


- a. In Windows:
  - 1) Navigate to the Control Panel.
  - 2) Double-click on Java.
  - 3) In the Java Control Panel:
    - i) Click the About... button.
    - ii) Check to see if the version is 1.4 or higher.
    - iii) Close the About Java window.
    - iv) If the version is lower than 1.4, select the *Update* tab.
    - v) Click the *Update Now* button.

### 9. Add the Executables to the Path Variable:

- a. In Windows:
  - 1) Navigate to the Control Panel.
  - 2) Double-click on System.
  - 3) Under System Properties:
    - i) Select the Advanced tab.
    - ii) Click on the Environment Variables button.



iii) In the *User Variable for <user>* window, scroll down to *path* and click the *Edit* button. If *path* does not appear, you may create it with the *New* button.



### iv) Scroll to the end of the list and add:

c:\ dsm2training\bin;c:\dsm2\_training\ptm\bin;c:\dsm2\_training\vista\bin Substitute drive letter or root location for C: as necessary. If you have a working vista installation you can skip the vista part and delete the vista directory from dsm2\_training.

